Windows Vista How to connect to Wireless Network

First verify if your Wireless Adapter has been installed correctly and enabled. To do that click on the **Start** button, locate "**Computer**" in the list, right-click on it and select "**Manage**". Click on **Device Manager**. If your wireless adapter is installed correctly you should see it under the "**Network Adapters**" category.

To connect to a wireless network click on the Start button and then on "Connect To".



You will see a list of available wireless networks in your area. Highlight the network you want to connect to (you can set the name of your wireless network (*SSID*) on your wireless access point or router). Click on "Connect"

(👰 Conr	nect to a network					
	Select a network to connect to						
	Sh	DW All	•		4,		
	2	D-Link ADSL Router	Security-enabled network		Î Uu		
	2	MainAP	Security-enabled network		.all		
					E		
	<u>Set up a (</u> Open Ne	connection or network twork and Sharing Cente	<u>er</u>				
				Connect	Cancel		

If your network is secured, you will be prompted to enter a security key or a passphrase. You will need to enter exactly the same security key or passphrase that you have set on your wireless access point or router. After typing in the key you can click on "**Display characters**" to verify that you've entered it correctly. Click on **Connect**.

0	👰 Connect to a network	
	Type the network security key or passphrase for	or D-Link ADSL Router
	The person who setup the network can give you the key or particular the set of particular the set of the set o	assphrase.
	Security key or passphrase:	
	•••••	
	Display characters	
	If you have a <u>USB flash drive</u> with network settings for now.	or D-Link ADSL Router, insert it
		Connect Cancel

After verifying the security key your computer will get connected to the selected wireless network.

Connect to a network	
Successfully connected to D-Link ADSL Router	
Save this network	
	Close



If the wireless settings on your wireless access point or router has been changed, you will need to remove the saved network profile and then reconnect to the network with the new settings. Go to *Control Panel > Network and Internet > Network and Sharing Centre*. Click on Manage wireless networks.

🔾 🗢 😟 🕨 Control Panel 🕨	Network and Internet Network	and Sharing Center	
Tasks View computers and devices	Network and Sharing Co	enter	View full man
Connect to a network Manage wireless networks	>		
Set up a connection or network Manage network connections	DAUS-PC (This compute	D-Link ADSL Router In ar)	nternet
Diagnose and repair	🏠 D-Link ADSL Router (Priv	/ate network)	Customize
	Access	Local and Internet	
	Connection	Wireless Network Connection 7 (D-Link ADSL Router)	View status
		Jignal strength: Excellent	Disconnect
	Sharing and Discovery		
	Network discovery	• On	$\overline{\mathbf{v}}$
	File sharing	• On	
	Public folder sharing	On (password required)	
See also	Printer sharing	On (password required)	$\overline{\mathbf{v}}$
Internet Options	Password protected sharing	On On	\checkmark
			~

Right-click on the network you want to remove and select "Remove network". Then reconnect to the network using the new settings.

Control Pane	I 🕨 Manage Wireless Networks	•	Search	Q		
Manage wireless networks that use (Wireless Network Connection 8) Windows tries to connect to these networks in the order listed below. To change the order, drag a network up or down in the list. You can also add or remove network profiles.						
🛟 Add 📼 Remove 👆 Mo	ve down 🛞 Adapter properties	🚴 Profile types 🛛 🙀 Ne	twork and Sharing Cente	r 🔞		
Networks you can view and mod	анту (2)	Turse Any suppo	T			
	Properties	Type: Any suppo	rted	Automatically con		
	Remove network	>				
D-Link ADSL Router	Rename	Type: Any supported	Automatically con			
	Move down					
DLINK Profile nam Security typ Radio typ	ne: DLINK Mode De: Unsecured De: Any supported	: Automatically connect				

