

# **Configuring a DWL-900AP+ as a Repeater**

Version 1.1

Created by: Scott Howell

Date: 17/12/03


This guide has been created to help you setup a DWL-900AP+ as a repeater for another DWL-900AP+. First of all we will need two units and as a minimum must have the below firmware:

**Revision B:** Version 2.61, **Revision C:** Version 3.06

You can determine the revision you have by flipping over the unit and looking at the silver sticker underneath the unit. Both of these firmware versions can be downloaded from here:

<http://www.dlink.com.au/tech/drivers/files/wireless/dwl900ap+.htm>

Once the units have been updated to this version we can commence the setup for a repeater.



## Step 1: Configuring the DWL-900AP+ #1 in AP Mode



The image shows the web-based configuration interface for a D-Link DWL-900AP+ Enhanced 2.4GHz Wireless Access Point. The interface has a blue header with the D-Link logo and the product name. Below the header is a navigation bar with tabs: Home (selected), Advanced, Tools, Status, and Help. On the left side, there is a sidebar with icons for Wizard, Wireless (highlighted in yellow), LAN, and DHCP. The main configuration area contains the following settings:

- AP Name : DWL-900AP+
- SSID : 900repeat
- Channel : 1
- WEP : ☐ Enabled ☒ Disabled
- WEP Encryption : 64Bit
- Key Type : HEX
- Key1 : ☒ 0000000000
- Key2 : ☐ 0000000000
- Key3 : ☐ 0000000000
- Key4 : ☐ 0000000000

At the bottom right, there are three buttons: Apply (with a green checkmark icon), Cancel (with an orange X icon), and Help (with a red plus icon).

For this example we will be using the main AP configured with the settings below: (shown above in picture)

IP Address: 192.168.0.50

AP Name: DWL-900AP+

SSID: 900repeat

Channel: 1

WEP: Disabled

Make sure once all the settings are entered that you click the "Apply" button so that it can save the configuration into the Access Point.

Once this has been configured we can move onto the repeater setup.


## Step 2: Configuring the second DWL-900AP+ #2 as a Repeater

First of all what we will need to do is change the IP address of the DWL-900AP+ that is to be used as a repeater. For this example we will make it 192.168.0.51, this way it will not conflict with another unit. Change the name of the unit (AP Name) to something different from the AP#1 name, e.g. "Repeater". Set the SSID to be identical to SSID on DWL-900AP+ #1 ("900repeat" in our example).

Now we will need to configure the unit as a repeater. This is done by logging into the unit and going to the **Advanced > Mode** page of the DWL-900AP+.

In order for this second DWL-900AP+ to connect we will need to select the **Repeater** option from the list then enter the LAN MAC address of the main DWL-900AP+ #1 into the Remote AP MAC field (shown below).


To verify the MAC address of DWL-900AP+ #1, you can select **Wireless Client Mode** and then click on **Site Survey** button: new window will pop up where you should be able to see your DWL-900AP+ #1 and its MAC address. Write down the MAC address, then close the site survey window, select **Repeater** mode and enter the MAC address that you have written down.



The screenshot shows the D-Link DWL-900AP+ web interface. The top header includes the D-Link logo and the product name "DWL-900AP+ Enhanced 2.4GHz Wireless Access Point". The navigation tabs are "Home", "Advanced" (selected), "Tools", "Status", and "Help". On the left sidebar, there are buttons for "Mode" (selected), "Performance", "Filters", and "802.1X". The main content area is titled "AP Mode" and lists four options: "Access Point", "Wireless Client", "Wireless Bridge", and "Repeater" (selected). To the right of these options are input fields for "Remote AP MAC", "Remote Bridge MAC", and "Remote AP MAC" (for the Repeater mode). The "Remote AP MAC" field for the Repeater mode contains the value "004005C86BD9". There is a "Site Survey" button next to the first "Remote AP MAC" field. At the bottom right, there are three buttons: "Apply" (with a green checkmark icon), "Cancel" (with an orange X icon), and "Help" (with a red plus icon).

Then make sure that you click "Apply" so that the settings are saved into the unit.

Now if you are using one of the D-Link wireless adapters, open D-Link Air Utility and select Site Survey. What you should see in the site survey table is something similar to this:



The reason that you see two wireless networks with the same SSID is because we have the main DWL-900AP+ #1 and also the DWL-900AP+ #2 as the repeater, which is retransmitting the signal with the same SSID.

So now when you move away and out of range of the Main DWL-900AP+ #1 you will only see one in the list (the DWL-900AP+ #2). So this will be the one you connect to in order to get a connection back to the Main DWL-900AP+ #1.

That's basically all that needs to be done in order to setup the repeater. The next step would be securing the connection and enabling encryption with the same key on all wireless devices.

Once the DWL-900AP+ is set to repeater mode, it becomes a transparent device and will no longer be able to be configured from a wireless connection. You must use a computer that is wired into the network or directly to the DWL-900AP+.

## For Advanced Users:

**Step 1:** From a wired computer, open your web browser such as Internet Explorer and enter the IP address of the DWL-900AP+ (<http://192.168.0.50>).

**Step 2:** Enter username (default username is "admin") and password (there is no default password).

**Step 3:** Click on Advanced at the top and then click Mode on the left side.

**Step 4:** Select Repeater and then enter the LAN (Ethernet) MAC address of the access point or wireless router you are connecting to. Click Apply and then click Continue.

**Note:** The DWL-900AP+ in repeater mode will currently connect to another DWL-900AP+ (in AP mode only), DWL-1000AP+ (in AP mode only), DWL-1500, DI-764, DI-714P+, or a DI-614+ wireless router.

**Note 2:** You cannot daisy chain Access Points in Repeater mode.